OberliTiffView / OberliTiffViewOCR V2.23: Registry entries

1 General entries (HKEY_LOCAL_MACHINE)

OberliTiffView:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffView\Misc\

OberliTiffViewOCR:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffViewOCR\Misc\

Name	Туре	Content
Name	String	Name of the licensee.
		This value must be taken from the license information sheet.
License	String	License code.
		This value must be taken from the license information sheet.
HideSaveAs	DWORD	1 = The File / Save as menu item and the Save as icon are not displayed.
		Value not equal to 1: The <i>File / Save as</i> menu item and the Save as icon are displayed.
		Default: 0
HideDocNavigation	DWORD	1 = The File / Next file and File / Previous file menu items and the associated icons are not displayed.
		Value not equal to 1: The menu items File / Next file and File / Previous file and the associated icons are displayed.
		Default: 0
HideSendMail	DWORD	1 = The File / Send by mail menu item and the associated icon are not displayed.
		Value not equal to 1: The File / Send by mail menu item and the associated icon are displayed.
		Default: 0
HideMailOptions	DWORD	1 = The Options / Mail menu item is not displayed.
		Value not equal to 1: The Options / Mail menu item is displayed.
		Default: 0

2 General entries (HKEY_LOCAL_MACHINE & HKEY_CURRENT_USER)

OberliTiffView:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffView\Misc\ and HKEY_CURRENT_USER\Software\Obeng\TiffView\Misc\

OberliTiffViewOCR:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffViewOCR\Misc\ and HKEY_CURRENT_USER\Software\Obeng\TiffViewOCR\Misc\

Name	Туре	Content	
About	DWORD	 0 = The About dialog is displayed when the program is started. 1 = The About dialog is not displayed when the program is started. Default: 0 	
Language	DWORD	0 = OberliTiffView / OberliTiffViewOCR is started with a German user interface. 1 = OberliTiffView / OberliTiffViewOCR is started with an English user interface.	
Maximized	DWORD	 0 = OberliTiffView / OberliTiffViewOCR is not started maximized. 1 = OberliTiffView / OberliTiffViewOCR is started maximized. The current value is saved when you exit OberliTiffView / OberliTiffViewOCR. Default: 0 	
PosX1Max, PosX2Max	DWORD	Position of the maximized main window. The two values are required to display <i>OberliTiffView / OberliTiffViewOCR</i> on the correct screen after the program start.	
PosX1, PosX2, PosY1, PosY2	DWORD	P Position and size of the main window in which OberliTiffView / OberliTiffViewOCR is displayed after starting the program. Prerequisite: OberliTiffView / OberliTiffViewOCR was not in the maximized view when last exited. When you exit OberliTiffView / OberliTiffViewOCR the current size and position of the main window are saved.	
MailPrg	String	Path/name of the mail program. Example Outlook 2010: C:\Program Files\Microsoft Office\Office14\OUTLOOK.EXE	
MailPrgArgs	String	Command line arguments to be given to the mail program when the Send by mail function is called. Placeholder:	

3 Thumbnails

OberliTiffView:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffView\Thumb\ und HKEY_CURRENT_USER\Software\Obeng\TiffView\Thumb\

OberliTiffViewOCR:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffViewOCR\Thumb\ und HKEY_CURRENT_USER\Software\Obeng\TiffViewOCR\Thumb\

Data fields:

Name	Туре	Content	
Align	DWORD	Alignment of the bar with the preview images. 0 = vertical left 1 = horizontal bottom 2 = vertical right 3 = horizontal top Default: 0	
On	DWORD	Show/hide the preview images. 0 = The bar with the preview images is not displayed. 1 = The bar with the preview images is displayed. Default: 1	
Quality	DWORD	Quality in which the preview images are displayed. 0 = Low 1 = Medium 2 = Hight Default: 0 (= Low)	
Width	DWORD	Width of the preview images in pixels. Range: 100 - 500 Default: 150	

Changes only become active after a restart of OberliTiffView / OberliTiffViewOCR.

4 Detail pictures

OberliTiffView:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffView\Image\ and HKEY_CURRENT_USER\Software\Obeng\TiffView\Image\

OberliTiffViewOCR:

HKEY_LOCAL_MACHINE\Software\Obeng\TiffViewOCR\Image\ and HKEY_CURRENT_USER\Software\Obeng\TiffViewOCR\Image\

Name	Туре	Content
HorizontalAlign	DWORD	Horizontal alignment of the detail screen.
		0 = centered
		1 = left
		Default: 0
VerticalAlign	DWORD	Vertical alignment of the detail screen.
		0 = centered
		1 = top
		Default: 1
StartupPageZoom	DWORD	Zoom factor to be used after starting the program.
		1 = Full page: Page is fully visible.
		2 = Width: The page is displayed in such a way that the entire width of the workspace is utilized. The page is normally not fully visible in height in this mode.

5 Accessibility

OberliTiffView:

HKEY_CURRENT_USER\Software\Obeng\TiffView\Accessibility\

OberliTiffViewOCR:

HKEY_CURRENT_USER\Software\Obeng\TiffViewOCR\Accessibility\

Data fields:

Name	Туре	Content
FullAccessibility	DWORD	Activate/deactivate additional functions for accessibility.
		0 = switched off
		1 = switched on
		Default: 0
		Available since V2.16
ShowPageRotationInToolbar	DWORD	Switching the display of the rotation of the current page in ° in the toolbar on/off.
		0 = Rotation in ° is not displayed
		1 = Rotation in ° is displayed
		Default: 0
		Available since V2.16

6 Logging

OberliTiffView:

HKEY_CURRENT_USER\Software\Obeng\TiffView\Logging\

OberliTiffViewOCR:

HKEY_CURRENT_USER\Software\Obeng\TiffViewOCR\Logging\

Name	Туре	Content
LoggingOn	DWORD	Switch extended logging on/off.
		0 = switched off
		1 = switched on
		Default: 0
		Available since V2.16

7 Reading the entries

Entries, which can be present in both HKEY_LOCAL_MACHINE and HKEY_CURRENT_USER, are read from the registry as follows:

- 1) The entry is searched for in HKEY_LOCAL_MACHINE. If the entry is found, the value from HKEY_LOCAL_MACHINE is read and used.
- 2) If the entry is not found in HKEY_LOCAL_MACHINE, it is searched for in HKEY_CURRENT_USER. If the entry is found, the value from HKEY_CURRENT_USER is read and used.
- 3) If the entry is also not found in HKEY_CURRENT_USER, the default value is used.